Bayesian Cluster Tool

Generated by Doxygen 1.8.17

Tue Oct 11 2022 13:16:17

1 Class Index	1
1.1 Class List	1
2 Class Documentation	3
2.1 Cluster Class Reference	3
2.1.1 Detailed Description	4
2.1.2 Constructor & Destructor Documentation	4
2.1.2.1 Cluster()	4
2.1.3 Member Function Documentation	4
2.1.3.1 GetParent()	4
2.1.3.2 operator+=()	5
2.2 Configuration Class Reference	5
2.2.1 Detailed Description	9
2.2.2 Member Function Documentation	9
2.2.2.1 alpha()	10
2.2.2.2 ClusterR()	10
2.2.2.3 ClusterT()	10
2.2.2.4 dR()	11
2.2.2.5 dT()	11
2.2.2.6 FromCommandline()	11
2.2.2.7 inputFile()	12
2.2.2.8 log_probability_sigma() [1/2]	12
2.2.2.9 log_probability_sigma() [2/2]	12
2.2.2.10 logAlpha()	13
2.2.2.11 logGammaAlpha()	13
2.2.2.12 logPb()	14
2.2.2.13 logPbDagger()	14
2.2.2.14 max2R()	14
2.2.2.15 max2R2()	15
2.2.2.16 maxR()	15
2.2.2.17 maxR2()	15
2.2.2.18 maxScanR()	16
2.2.2.19 maxScanT()	16
2.2.2.20 minScanR()	16
2.2.2.21 minScanT()	17
2.2.2.22 outputFile()	17
2.2.2.23 probability_sigma() [1/2]	17
2.2.2.24 probability_sigma() [2/2]	17
2.2.2.25 Rbins()	18
2.2.2.26 scale2()	18
2.2.2.27 SetAlpha()	18
2.2.2.28 SetCentre()	19

2.2.2.29 SetInputFile()	. 19
2.2.2.30 SetOutputFile()	. 20
2.2.2.31 SetPb()	. 20
2.2.2.32 SetRBins()	. 20
2.2.2.33 SetSigmaParameters()	. 21
2.2.2.34 SetTBins()	. 21
2.2.2.35 SetValidate()	. 22
2.2.2.36 SetZoom()	. 22
2.2.2.37 sigmabins() [1/2]	. 22
2.2.2.38 sigmabins() [2/2]	. 23
2.2.2.39 sigmabins2() [1/2]	. 23
2.2.2.40 sigmabins2() [2/2]	. 23
2.2.2.41 sigmacount()	. 24
2.2.2.42 sigmaspacing()	. 24
2.2.2.43 Tbins()	. 24
2.2.2.44 toAlgorithmUnits()	. 24
2.2.2.45 toAlgorithmX()	. 25
2.2.2.46 toAlgorithmY()	. 25
2.2.2.47 toPhysicalUnits()	. 26
2.2.2.48 toPhysicalX()	. 26
2.2.2.49 toPhysicalY()	. 27
2.2.2.50 validate()	. 27
2.3 Data Class Reference	. 28
2.3.1 Detailed Description	. 29
2.3.2 Constructor & Destructor Documentation	. 29
2.3.2.1 Data() [1/3]	. 29
2.3.2.2 Data() [2/3]	. 30
2.3.2.3 Data() [3/3]	. 30
2.3.3 Member Function Documentation	. 30
2.3.3.1 dPhi()	. 30
2.3.3.2 dR()	. 31
2.3.3.3 dR2()	. 31
2.3.3.4 operator<()	. 32
2.3.3.5 operator=() [1/2]	. 32
2.3.3.6 operator=() [2/2]	. 32
2.3.3.7 Preprocess()	. 33
2.4 DataProxy Class Reference	
2.4.1 Detailed Description	. 35
2.4.2 Constructor & Destructor Documentation	
2.4.2.1 DataProxy() [1/3]	
2.4.2.2 DataProxy() [2/3]	. 35
2.4.2.3 DataProxy() [3/3]	. 35

2.4.3 Member Function Documentation	. 36
2.4.3.1 Clusterize() [1/2]	. 36
2.4.3.2 Clusterize() [2/2]	. 36
2.4.3.3 GetCluster()	. 37
2.4.3.4 operator=() [1/2]	. 37
2.4.3.5 operator=() [2/2]	. 37
2.5 Event Class Reference	. 38
2.5.1 Detailed Description	. 39
2.5.2 Constructor & Destructor Documentation	. 39
2.5.2.1 Event() [1/2]	. 39
2.5.2.2 Event() [2/2]	. 39
2.5.3 Member Function Documentation	. 39
2.5.3.1 Clusterize()	. 39
2.5.3.2 LoadCSV()	. 40
2.5.3.3 operator=() [1/2]	. 40
2.5.3.4 operator=() [2/2]	. 41
2.5.3.5 ScanRT()	. 41
2.5.3.6 WriteCSV()	. 41
2.6 EventProxy Class Reference	. 42
2.6.1 Detailed Description	. 43
2.6.2 Constructor & Destructor Documentation	. 43
2.6.2.1 EventProxy() [1/3]	. 43
2.6.2.2 EventProxy() [2/3]	. 44
2.6.2.3 EventProxy() [3/3]	. 44
2.6.3 Member Function Documentation	. 44
2.6.3.1 CheckClusterization()	. 44
2.6.3.2 Clusterize()	. 45
2.6.3.3 GetData()	. 45
2.6.3.4 operator=() [1/2]	. 45
2.6.3.5 operator=() [2/2]	. 46
2.6.3.6 ScanRT()	. 46
2.7 Cluster::Parameter Struct Reference	. 47
2.7.1 Detailed Description	. 47
2.7.2 Member Function Documentation	. 47
2.7.2.1 log_score()	. 48
2.7.2.2 operator+=()	. 48
2.8 ProgressBar Struct Reference	. 48
2.8.1 Detailed Description	. 49
2.8.2 Constructor & Destructor Documentation	. 49
2.8.2.1 ProgressBar()	. 49
2.8.3 Member Function Documentation	. 50
2.8.3.1 operator++()	. 50

2.9	ProgressBar2 Struct Reference	50
	2.9.1 Detailed Description	51
	2.9.2 Constructor & Destructor Documentation	51
	2.9.2.1 ProgressBar2()	51
	2.9.3 Member Function Documentation	51
	2.9.3.1 operator++()	51
Index		53

Chapter 1

Class Index

1.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Cluster
A class representing a cluster
Configuration
Class for storing the configuration parameters
Data
A class to store the raw data-points
DataProxy
A light-weight proxy for the raw data-points
Event
A class which holds the raw event data and global parameters
EventProxy
A lightweight wrapper for the event to store clusters for a given scan
Cluster::Parameter
A struct representing the cluster parameters
ProgressBar
A utility progress-bar
ProgressBar2
A utility code timer

2 Class Index

Chapter 2

Class Documentation

2.1 Cluster Class Reference

A class representing a cluster.

```
#include <Cluster.hpp>
```

Collaboration diagram for Cluster:



Classes

struct Parameter

A struct representing the cluster parameters.

Public Member Functions

• Cluster ()

Default constructor.

• Cluster (const Data &aData)

Construct a cluster from a single data-point.

Cluster & operator+= (const Cluster &aOther)

Add another cluster to this one.

• Cluster * GetParent ()

Get a pointer to this cluster's ultimate parent.

• void UpdateLogScore ()

Update log-probability after a scan.

Public Attributes

• std::vector< Parameter > mParams

The collection of parameters, each corresponding to a different sigma hypothesis.

• std::size_t mClusterSize

The number of points in the current cluster.

• std::size_t mLastClusterSize

The number of points in the cluster on the previous scan iteration.

• PRECISION mClusterScore

The log-probability of the current cluster.

Cluster * mParent

A pointer to the immediate parent of the current cluster.

2.1.1 Detailed Description

A class representing a cluster.

Definition at line 14 of file Cluster.hpp.

2.1.2 Constructor & Destructor Documentation

2.1.2.1 Cluster()

Construct a cluster from a single data-point.

Parameters

aData	A data-point with which to initialize the cluster

Definition at line 61 of file Cluster.cpp.

References Configuration::Instance, mParams, Data::r2, Data::x, Data::x, and Data::y.

2.1.3 Member Function Documentation

2.1.3.1 GetParent()

```
Cluster * Cluster::GetParent ( )
```

Get a pointer to this cluster's ultimate parent.

Returns

A pointer to this cluster's ultimate parent

Definition at line 116 of file Cluster.cpp.

References GetParent(), and mParent.

Referenced by DataProxy::GetCluster(), and GetParent().

2.1.3.2 operator+=()

Add another cluster to this one.

Parameters

aOther Another cluster of parameters to add to this one

Returns

Reference to this, for chaining calls

Definition at line 102 of file Cluster.cpp.

References mClusterSize, and mParams.

The documentation for this class was generated from the following files:

- · include/BayesianClustering/Cluster.hpp
- · src/BayesianClustering/Cluster.cpp

2.2 Configuration Class Reference

Class for storing the configuration parameters.

```
#include <Configuration.hpp>
```

Collaboration diagram for Configuration:

Configuration Instance

Public Member Functions

Configuration ()

Default constructor.

void SetCentre (const double &aPhysicalCentreX, const double &aPhysicalCentreY)

Setter for the centre of the scan window.

void SetZoom (const double &aScale)

Setter for the half-width of the scan window.

void SetSigmaParameters (const std::size_t &aSigmacount, const double &aSigmaMin, const double &a
 SigmaMax, const std::function < double (const double &) > &aInterpolator)

Setter for the sigma-bins to be integrated over.

• void SetRBins (const std::size_t &aRbins, const double &aMinScanR=0.0, const double &aMaxScanR=-1)

Setter for the R bins for the RT scan.

- void SetTBins (const std::size_t &aTbins, const double &aMinScanT=0.0, const double &aMaxScanT=-1)
- void SetPb (const double &aPB)

Setter for the P_b parameter.

void SetAlpha (const double &aAlpha)

Setter for the alpha parameter.

void SetValidate (const bool &aValidate)

Set whether to validate clusterization.

void SetInputFile (const std::string &aFileName)

Setter for the input file.

void SetOutputFile (const std::string &aFileName)

Setter for the output file.

void FromCommandline (int argc, char **argv)

Parse the parameters when passed in as commandline arguments.

· const double & scale2 () const

Getter for the scale-parameter squared.

• const std::size_t & sigmacount () const

Getter for the sigma count.

const double & sigmaspacing () const

Getter for the sigma spacing.

• const std::vector< double > & sigmabins () const

Getter for the values of sigma.

const std::vector< double > & sigmabins2 () const

Getter for the values of sigma squared.

const std::vector< double > & probability_sigma () const

Getter for the probabilities of a given sigma.

const std::vector< double > & log_probability_sigma () const

Getter for the log of the probabilities of a given sigma.

• const double & sigmabins (const std::size_t &i) const

Getter for the i'th value of sigma.

const double & sigmabins2 (const std::size_t &i) const

Getter for the i'th value of sigma squared.

const double & probability sigma (const std::size t &i) const

Getter for the probability of the i'th value of sigma.

const double & log_probability_sigma (const std::size_t &i) const

Getter for the log-probability of the i'th value of sigma.

· const double & maxR () const

Getter for the maximum value of R.

const double & maxR2 () const

Getter for the maximum value of R squared.

• const double & max2R () const

Getter for the maximum value of 2R.

· const double & max2R2 () const

Getter for the maximum value of 2R squared.

const double & minScanR () const

Getter for the lowest value of R to scan.

const double & maxScanR () const

Getter for the highest value of R to scan.

const double & minScanT () const

Getter for the lowest value of T to scan.

const double & maxScanT () const

Getter for the highest value of T to scan.

• const double & dR () const

Getter for the spacing of value of R to scan.

· const std::size_t & Rbins () const

Getter for the number of R values to scan.

• const double & dT () const

Getter for the spacing of value of T to scan.

const std::size t & Tbins () const

Getter for the number of T values to scan.

const double & logPb () const

Logarithm of the P_b parameter

· const double & logPbDagger () const

Logarithm of the (1 - P_b) parameter

· const double & alpha () const

Getter for the alpha parameter

• const double & logAlpha () const

Getter for the logarithm of the alpha parameter

· const double & logGammaAlpha () const

Getter for the logarithm of the gamma function of alpha parameter

· const bool & validate () const

Getter for whether or not to run the validation on the clustering.

• const std::string & inputFile () const

Getter for the input file.

const std::string & outputFile () const

Getter for the output file.

• const double & ClusterR () const

Getter for the R value for a clusterization pass.

const double & ClusterT () const

Getter for the T value for a clusterization pass.

· double toPhysicalUnits (const double &aAlgorithmUnits) const

Utility function to convert a normalized algorithm distance to physical distance.

double toAlgorithmUnits (const double &aPhysicalUnits) const

Utility function to convert physical distances to a normalized algorithm distances.

• double toPhysicalX (const double &aAlgorithmX) const

Utility function to convert a normalized algorithm x-coordinate to a physical x-coordinate.

double toAlgorithmX (const double &aPhysicalX) const

Utility function to convert a physical x-coordinate to a normalized algorithm x-coordinate.

double toPhysicalY (const double &aAlgorithmY) const

Utility function to convert a normalized algorithm y-coordinate to a physical y-coordinate.

double toAlgorithmY (const double &aPhysicalY) const

Utility function to convert a physical y-coordinate to a normalized algorithm y-coordinate.

Static Public Attributes

· static Configuration Instance

A single global copy of the global variables.

Private Attributes

· double mScale

The scale parameter.

double mScale2

The scale parameter squared.

· double mPhysicalCentreX

The x-coordinate of the centre of the window in physical units.

· double mPhysicalCentreY

The y-coordinate of the centre of the window in physical units.

· std::size_t mSigmacount

The number of sigma bins.

• double mSigmaspacing

The spacing of sigma bins.

• std::vector< double > mSigmabins

The values of sigma.

 $\bullet \quad \text{std::vector} < \text{double} > \text{mSigmabins2}$

The values of sigma squared.

• std::vector< double > mProbabilitySigma

The probability of a given sigma.

std::vector< double > mLogProbabilitySigma

The log-probability of a gievn sigma.

double mMaxR

The maximum value of R.

double mMaxR2

The maximum value of R squared.

double mMax2R

The maximum value of 2R

double mMax2R2

The maximum value of 2R squared.

· double mMinScanR

The lowest value of R to scan.

double mMaxScanR

The largest value of R to scan.

· double mMinScanT

The lowest value of T to scan.

• double mMaxScanT

The largest value of T to scan.

double mDR

The spacing of value of R to scan.

double mDT

The spacing of value of T to scan.

• std::size_t mRbins

The number of R values to scan.

std::size_t mTbins

The number of T values to scan.

double mAlpha

The alpha parameter.

· double mLogAlpha

Logarithm of the alpha parameter.

• double mLogGammaAlpha

Logarithm of the gamma function of alpha parameter

double mLogPb

Logarithm of the P_b parameter

• double mLogPbDagger

Logarithm of the(1- P_b) parameter

bool mValidate

Whether or not to run the validation on the clustering.

• std::string mInputFile

The input event file.

• std::string mOutputFile

The output file.

double mClusterR

The value of R for clustering.

• double mClusterT

The value of T for clustering.

2.2.1 Detailed Description

Class for storing the configuration parameters.

Definition at line 71 of file Configuration.hpp.

2.2.2 Member Function Documentation

2.2.2.1 alpha()

```
const double& Configuration::alpha ( ) const [inline]
```

Getter for the alpha parameter

Returns

The alpha parameter

Definition at line 221 of file Configuration.hpp.

References mAlpha.

2.2.2.2 ClusterR()

```
const double& Configuration::ClusterR ( ) const [inline]
```

Getter for the R value for a clusterization pass.

Returns

The R value for a clusterization pass

Definition at line 244 of file Configuration.hpp.

References mClusterR.

2.2.2.3 ClusterT()

```
const double& Configuration::ClusterT ( ) const [inline]
```

Getter for the T value for a clusterization pass.

Returns

The T value for a clusterization pass

Definition at line 247 of file Configuration.hpp.

References mClusterT.

2.2.2.4 dR()

```
const double& Configuration::dR ( ) const [inline]
```

Getter for the spacing of value of R to scan.

Returns

The spacing of value of R to scan

Definition at line 201 of file Configuration.hpp.

References mDR.

2.2.2.5 dT()

```
const double& Configuration::dT ( ) const [inline]
```

Getter for the spacing of value of T to scan.

Returns

The spacing of value of T to scan

Definition at line 207 of file Configuration.hpp.

References mDT.

Referenced by EventProxy::ScanRT().

2.2.2.6 FromCommandline()

Parse the parameters when passed in as commandline arguments.

Parameters

argc	The number of commandline arguments
argv	The commandline arguments

Definition at line 149 of file Configuration.cpp.

References mClusterR, mClusterT, SetAlpha(), SetCentre(), SetInputFile(), SetOutputFile(), SetPb(), SetRBins(), SetSigmaParameters(), SetTBins(), SetValidate(), SetZoom(), and toAlgorithmUnits().

2.2.2.7 inputFile()

```
const std::string& Configuration::inputFile ( ) const [inline]
```

Getter for the input file.

Returns

The name of the input event file

Definition at line 236 of file Configuration.hpp.

References mInputFile.

Referenced by Event::Event().

2.2.2.8 log_probability_sigma() [1/2]

```
\verb|const| std::vector<| double > & Configuration::log_probability_sigma () const [inline]|
```

Getter for the log of the probabilities of a given sigma.

Returns

The log of the probabilities of given sigma

Definition at line 154 of file Configuration.hpp.

References mLogProbabilitySigma.

2.2.2.9 log_probability_sigma() [2/2]

Getter for the log-probability of the i'th value of sigma.

Parameters

i The index of the value of sigma to get the log-probability for

Returns

The log-probability of sigma_i

Definition at line 171 of file Configuration.hpp.

References mLogProbabilitySigma.

2.2.2.10 logAlpha()

```
const double& Configuration::logAlpha ( ) const [inline]
```

Getter for the logarithm of the alpha parameter

Returns

The logarithm of the alpha parameter

Definition at line 224 of file Configuration.hpp.

References mLogAlpha.

2.2.2.11 logGammaAlpha()

```
const double& Configuration::logGammaAlpha ( ) const [inline]
```

Getter for the logarithm of the gamma function of alpha parameter

Returns

The logarithm of the gamma function of alpha parameter

Definition at line 227 of file Configuration.hpp.

References mLogGammaAlpha.

2.2.2.12 logPb()

```
const double& Configuration::logPb ( ) const [inline]
```

Logarithm of the P_b parameter

Returns

Logarithm of the P_b parameter

Definition at line 214 of file Configuration.hpp.

References mLogPb.

Referenced by EventProxy::UpdateLogScore().

2.2.2.13 logPbDagger()

```
const double& Configuration::logPbDagger ( ) const [inline]
```

Logarithm of the (1 - P_b) parameter

Returns

Logarithm of the (1 - P_b) parameter

Definition at line 217 of file Configuration.hpp.

References mLogPbDagger.

2.2.2.14 max2R()

```
const double& Configuration::max2R ( ) const [inline]
```

Getter for the maximum value of 2R.

Returns

The maximum value of 2R

Definition at line 181 of file Configuration.hpp.

References mMax2R.

Referenced by Data::Preprocess().

2.2.2.15 max2R2()

```
const double& Configuration::max2R2 ( ) const [inline]
```

Getter for the maximum value of 2R squared.

Returns

The maximum value of 2R squared

Definition at line 184 of file Configuration.hpp.

References mMax2R2.

2.2.2.16 maxR()

```
const double& Configuration::maxR ( ) const [inline]
```

Getter for the maximum value of R.

Returns

The maximum value of R

Definition at line 175 of file Configuration.hpp.

References mMaxR.

2.2.2.17 maxR2()

```
const double& Configuration::maxR2 ( ) const [inline]
```

Getter for the maximum value of R squared.

Returns

The maximum value of R squared

Definition at line 178 of file Configuration.hpp.

References mMaxR2.

2.2.2.18 maxScanR()

```
const double& Configuration::maxScanR ( ) const [inline]
```

Getter for the highest value of R to scan.

Returns

The highest value of R to scan

Definition at line 191 of file Configuration.hpp.

References mMaxScanR.

2.2.2.19 maxScanT()

```
const double& Configuration::maxScanT ( ) const [inline]
```

Getter for the highest value of T to scan.

Returns

The highest value of T to scan

Definition at line 197 of file Configuration.hpp.

References mMaxScanT.

Referenced by EventProxy::ScanRT().

2.2.2.20 minScanR()

```
const double& Configuration::minScanR ( ) const [inline]
```

Getter for the lowest value of R to scan.

Returns

The lowest value of R to scan

Definition at line 188 of file Configuration.hpp.

References mMinScanR.

2.2.2.21 minScanT()

```
const double& Configuration::minScanT ( ) const [inline]
```

Getter for the lowest value of T to scan.

Returns

The lowest value of T to scan

Definition at line 194 of file Configuration.hpp.

References mMinScanT.

2.2.2.22 outputFile()

```
const std::string& Configuration::outputFile ( ) const [inline]
```

Getter for the output file.

Returns

The name of the output file

Definition at line 239 of file Configuration.hpp.

References mOutputFile.

2.2.2.23 probability_sigma() [1/2]

```
const std::vector< double >& Configuration::probability_sigma ( ) const [inline]
```

Getter for the probabilities of a given sigma.

Returns

The probabilities of given sigma

Definition at line 151 of file Configuration.hpp.

References mProbabilitySigma.

2.2.2.24 probability_sigma() [2/2]

```
const double % Configuration::probability_sigma ( const std::size_t & i ) const [inline]
```

Getter for the probability of the i'th value of sigma.

Parameters

i The index of the value of sigma to get the probability for

Returns

The probability of sigma_i

Definition at line 167 of file Configuration.hpp.

References mProbabilitySigma.

2.2.2.25 Rbins()

```
const std::size_t& Configuration::Rbins ( ) const [inline]
```

Getter for the number of R values to scan.

Returns

The number of R values to scan

Definition at line 204 of file Configuration.hpp.

References mRbins.

Referenced by EventProxy::ScanRT().

2.2.2.26 scale2()

```
const double& Configuration::scale2 ( ) const [inline]
```

Getter for the scale-parameter squared.

Returns

The scale-parameter squared

Definition at line 133 of file Configuration.hpp.

References mScale2.

2.2.2.27 SetAlpha()

Setter for the alpha parameter.

Parameters

aAlpha	The alpha parameter
--------	---------------------

Definition at line 102 of file Configuration.cpp.

References mAlpha, mLogAlpha, and mLogGammaAlpha.

Referenced by FromCommandline().

2.2.2.28 SetCentre()

Setter for the centre of the scan window.

Parameters

aPhysicalCentreX	The x-coordinate of the centre of the window in physical units (becomes 0 in algorithm units)
aPhysicalCentreY	The y-coordinate of the centre of the window in physical units (becomes 0 in algorithm units)

Definition at line 38 of file Configuration.cpp.

References mPhysicalCentreX, and mPhysicalCentreY.

Referenced by FromCommandline().

2.2.2.29 SetInputFile()

Setter for the input file.

Parameters

aFileName	The name of the file

Definition at line 118 of file Configuration.cpp.

References mInputFile.

Referenced by FromCommandline().

2.2.2.30 SetOutputFile()

Setter for the output file.

Parameters

aFileName The name of the file

Definition at line 125 of file Configuration.cpp.

References mOutputFile.

Referenced by FromCommandline().

2.2.2.31 SetPb()

Setter for the P_b parameter.

Parameters

aPR	The P_b parameter
ai D	The I _b parameter

Definition at line 95 of file Configuration.cpp.

References mLogPb, and mLogPbDagger.

Referenced by FromCommandline().

2.2.2.32 SetRBins()

Setter for the R bins for the RT scan.

Parameters

aRbins	The number of R bins to scan over
aMinScanR	The lowest value of R to scan
aMaxScanR	The largest value of R to scan

Definition at line 70 of file Configuration.cpp.

References mDR, mMax2R, mMax2R, mMaxR, mMaxR2, mMaxScanR, mMinScanR, mRbins, toAlgorithmUnits(), and toPhysicalUnits().

Referenced by FromCommandline().

2.2.2.33 SetSigmaParameters()

Setter for the sigma-bins to be integrated over.

Parameters

aSigmacount	The number of sigma bins
aSigmaMin	The lowest sigma bin
aSigmaMax	The highest sigma bin
aInterpolator	Function-object to generate the probability of any given sigma

Definition at line 52 of file Configuration.cpp.

References mLogProbabilitySigma, mProbabilitySigma, mScale, mSigmabins, mSigmabins2, mSigmacount, m← Sigmaspacing, and toAlgorithmUnits().

Referenced by FromCommandline().

2.2.2.34 SetTBins()

Parameters

aTbins	The number of T bins to scan over
aMinScanT	The lowest value of T to scan
aMaxScanT	The largest value of T to scan

Definition at line 85 of file Configuration.cpp.

References mDT, mMaxScanT, mMinScanT, mTbins, toAlgorithmUnits(), and toPhysicalUnits().

Referenced by FromCommandline().

2.2.2.35 SetValidate()

Set whether to validate clusterization.

Parameters

aValidate Whether to validate clusterizatio

Definition at line 110 of file Configuration.cpp.

References mValidate.

Referenced by FromCommandline().

2.2.2.36 SetZoom()

Setter for the half-width of the scan window.

Parameters

aScale	The scale of the window in physical units (becomes ±1 in algorithm units)
--------	---

Definition at line 45 of file Configuration.cpp.

References mScale, and mScale2.

Referenced by FromCommandline().

2.2.2.37 sigmabins() [1/2]

```
const std::vector< double >& Configuration::sigmabins ( ) const [inline]
```

Getter for the values of sigma.

Returns

The values of sigma

Definition at line 145 of file Configuration.hpp.

References mSigmabins.

2.2.2.38 sigmabins() [2/2]

```
const double Configuration::sigmabins ( const std::size_t & i ) const [inline]
```

Getter for the i'th value of sigma.

Parameters

i The index of the value of sigma to get

Returns

The value of sigma_i

Definition at line 159 of file Configuration.hpp.

References mSigmabins.

2.2.2.39 sigmabins2() [1/2]

```
const std::vector< double >& Configuration::sigmabins2 ( ) const [inline]
```

Getter for the values of sigma squared.

Returns

The values of sigma squared

Definition at line 148 of file Configuration.hpp.

References mSigmabins2.

2.2.2.40 sigmabins2() [2/2]

Getter for the i'th value of sigma squared.

Parameters

i The index of the value of sigma squared to get

Returns

The value of sigma_i squared

Definition at line 163 of file Configuration.hpp.

References mSigmabins2.

2.2.2.41 sigmacount()

```
const std::size_t& Configuration::sigmacount ( ) const [inline]
```

Getter for the sigma count.

Returns

The sigma count

Definition at line 137 of file Configuration.hpp.

References mSigmacount.

Referenced by Cluster::UpdateLogScore().

2.2.2.42 sigmaspacing()

```
const double& Configuration::sigmaspacing ( ) const [inline]
```

Getter for the sigma spacing.

Returns

The sigma spacing

Definition at line 141 of file Configuration.hpp.

References mSigmaspacing.

2.2.2.43 Tbins()

```
const std::size_t& Configuration::Tbins ( ) const [inline]
```

Getter for the number of T values to scan.

Returns

The number of T values to scan

Definition at line 210 of file Configuration.hpp.

References mTbins.

Referenced by EventProxy::ScanRT().

2.2.2.44 toAlgorithmUnits()

Utility function to convert physical distances to a normalized algorithm distances.

Parameters

aPhysicalUnits	A physical distance
----------------	---------------------

Returns

A normalized algorithm distances

Definition at line 261 of file Configuration.hpp.

References mScale.

Referenced by FromCommandline(), SetRBins(), SetSigmaParameters(), SetTBins(), toAlgorithmX(), and to \leftarrow AlgorithmY().

2.2.2.45 toAlgorithmX()

Utility function to convert a physical x-coordinate to a normalized algorithm x-coordinate.

Parameters

aPhysicalX	A physical x-coordinate

Returns

A normalized x-coordinate

Definition at line 277 of file Configuration.hpp.

References mPhysicalCentreX, and toAlgorithmUnits().

2.2.2.46 toAlgorithmY()

Utility function to convert a physical y-coordinate to a normalized algorithm y-coordinate.

Parameters

Returns

A normalized y-coordinate

Definition at line 293 of file Configuration.hpp.

References mPhysicalCentreY, and toAlgorithmUnits().

2.2.2.47 toPhysicalUnits()

Utility function to convert a normalized algorithm distance to physical distance.

Parameters

aAlgorithmUnits	A normalized algorithm distance
-----------------	---------------------------------

Returns

A physical distances

Definition at line 253 of file Configuration.hpp.

References mScale.

Referenced by SetRBins(), SetTBins(), toPhysicalX(), toPhysicalY(), and Event::WriteCSV().

2.2.2.48 toPhysicalX()

Utility function to convert a normalized algorithm x-coordinate to a physical x-coordinate.

Parameters

```
aAlgorithmX A normalized x-coordinate
```

Returns

A physical x-coordinate

Definition at line 269 of file Configuration.hpp.

References mPhysicalCentreX, and toPhysicalUnits().

2.2.2.49 toPhysicalY()

Utility function to convert a normalized algorithm y-coordinate to a physical y-coordinate.

Parameters

aAlgorithmY	A normalized y-coordinate
-------------	---------------------------

Returns

A physical y-coordinate

Definition at line 285 of file Configuration.hpp.

References mPhysicalCentreY, and toPhysicalUnits().

Referenced by Event::WriteCSV().

2.2.2.50 validate()

```
const bool& Configuration::validate ( ) const [inline]
```

Getter for whether or not to run the validation on the clustering.

Returns

Whether or not to run the validation on the clustering

Definition at line 231 of file Configuration.hpp.

References mValidate.

The documentation for this class was generated from the following files:


- include/BayesianClustering/Configuration.hpp
- src/BayesianClustering/Configuration.cpp
- src/BayesianClustering/Event.cpp

2.3 Data Class Reference

A class to store the raw data-points.

#include <Data.hpp>

Collaboration diagram for Data:



Public Member Functions

Data (const PRECISION &aX, const PRECISION &aY, const PRECISION &aS)

Constructor.

• Data (const Data &aOther)=delete

Deleted copy constructor.

• Data & operator= (const Data &aOther)=delete

Deleted assignment operator.

• Data (Data &&aOther)=default

Default move constructor.

• Data & operator= (Data &&aOther)=default

Default move-assignment constructor.

virtual ~Data ()

Destructor.

• bool operator< (const Data &aOther) const

Comparison operator for sorting data-points by distance from the origin.

PRECISION dR2 (const Data &aOther) const

Return the squared-distance of this data-points from another.

PRECISION dR (const Data &aOther) const

Return the distance of this data-points from another.

PRECISION dPhi (const Data &aOther) const

Return the angle between this data-points and another.

void Preprocess (std::vector < Data > &aData, const std::size_t &aIndex)

All the necessary pre-processing to get this data-point ready for an RT-scan.

- void PreprocessLocalizationScores (std::vector < Data > &aData)
- PRECISION CalculateLocalizationScore (const std::vector< Data > &aData, const double &R) const

2.3 Data Class Reference 29

Public Attributes

• PRECISION x

The x-position of the data-point.

· PRECISION y

The y-position of the data-point.

• PRECISION S

The sigma of the data-point

• PRECISION r2

The squared radial distance of the data-point.

· PRECISION r

The radial distance of the data-point.

· PRECISION phi

The phi-position of the data-point.

std::vector< PRECISION > mLocalizationScores

The locaalization scores, one per R-bin.

• std::vector< std::pair< PRECISION, std::size_t >> mNeighbours

The list of neighbours as a pair of squared-distance and index into the list of points.

• Cluster * mProtoCluster

A cluster containing only this data-point.

2.3.1 Detailed Description

A class to store the raw data-points.

Definition at line 14 of file Data.hpp.

2.3.2 Constructor & Destructor Documentation

2.3.2.1 Data() [1/3]

```
Data::Data (

const PRECISION & aX,

const PRECISION & aY,

const PRECISION & aS)
```

Constructor.

Parameters

aX	The x-position of the data-point in algorithm units
aY	The y-position of the data-point in algorithm units
aS	The sigma of the data-point in algorithm units

Definition at line 13 of file Data.cpp.

2.3.2.2 Data() [2/3]

Deleted copy constructor.

Parameters

aOther Anonymous argument

2.3.2.3 Data() [3/3]

Default move constructor.

Parameters

aOther Anonymous argument

2.3.3 Member Function Documentation

2.3.3.1 dPhi()

Return the angle between this data-points and another.

Returns

The angle between this data-points and another

Parameters

aOther	A data-point to compare against

2.3 Data Class Reference 31

Definition at line 68 of file Data.hpp.

References phi.

2.3.3.2 dR()

Return the distance of this data-points from another.

Returns

The distance of this data-points from another

Parameters

aOther	A data-point to compare against

Definition at line 60 of file Data.hpp.

References dR2().

2.3.3.3 dR2()

Return the squared-distance of this data-points from another.

Returns

The squared-distance of this data-points from another

Parameters

aOther	A data-point to compare against

Definition at line 51 of file Data.hpp.

References x, and y.

Referenced by dR().

2.3.3.4 operator<()

Comparison operator for sorting data-points by distance from the origin.

Returns

Whether this data-point is closer to the origin than another

Parameters

aOther	A data-point to compare against

Definition at line 43 of file Data.hpp.

References r.

2.3.3.5 operator=() [1/2]

Deleted assignment operator.

Returns

Reference to this, for chaining calls

Parameters

```
aOther Anonymous argument
```

2.3.3.6 operator=() [2/2]

Default move-assignment constructor.

Returns

Reference to this, for chaining calls

Parameters

aOther Anonymous argu	ıment
-----------------------	-------

2.3.3.7 Preprocess()

All the necessary pre-processing to get this data-point ready for an RT-scan.

Parameters

aData	The collection of data-points
alndex	The index of the current data-point

Definition at line 27 of file Data.cpp.

References Configuration::Instance, and Configuration::max2R().

The documentation for this class was generated from the following files:


- include/BayesianClustering/Data.hpp
- src/BayesianClustering/Data.cpp

2.4 DataProxy Class Reference

A light-weight proxy for the raw data-points.

#include <DataProxy.hpp>

Collaboration diagram for DataProxy:



Public Member Functions

• DataProxy (Data &aData)

Default constructor.

• DataProxy (const DataProxy &aOther)=delete

Deleted copy constructor.

• DataProxy & operator= (const DataProxy &aOther)=delete

Deleted assignment operator.

DataProxy (DataProxy &&aOther)=default

Default move constructor.

• DataProxy & operator= (DataProxy &&aOther)=default

Default move-assignment constructor.

void Clusterize (const PRECISION &a2R2, EventProxy &aEvent)

Entry point clusterization function - a new cluster will be created.

void Clusterize (const PRECISION &a2R2, EventProxy &aEvent, Cluster *aCluster)

Recursive clusterization function.

Cluster * GetCluster ()

Get a pointer to this data-proxy's ultimate parent cluster (or null if unclustered.

Public Attributes

• Data * mData

The data-point for which this is the proxy.

Cluster * mCluster

This data-proxy's immediate parent cluster.

bool mExclude

Whether this data-point is to be included in the clusterization.

2.4.1 Detailed Description

A light-weight proxy for the raw data-points.

Definition at line 17 of file DataProxy.hpp.

2.4.2 Constructor & Destructor Documentation

2.4.2.1 DataProxy() [1/3]

Default constructor.

Parameters

aData The data-point for which this is the proxy
--

Definition at line 10 of file DataProxy.cpp.

2.4.2.2 DataProxy() [2/3]

Deleted copy constructor.

Parameters

```
aOther Anonymous argument
```

2.4.2.3 DataProxy() [3/3]

Default move constructor.

Parameters

aOther	Anonymous argument
--------	--------------------

2.4.3 Member Function Documentation

2.4.3.1 Clusterize() [1/2]

Entry point clusterization function - a new cluster will be created.

Parameters

a2R2	The clusterization radius
aEvent	The event-proxy in which we are running

Definition at line 15 of file DataProxy.cpp.

References mCluster, EventProxy::mClusters, and mExclude.

Referenced by Clusterize().

2.4.3.2 Clusterize() [2/2]

Recursive clusterization function.

Parameters

a2R2	The clusterization radius
aEvent	The event-proxy in which we are running
aCluster	The cluster we are building

Definition at line 23 of file DataProxy.cpp.

References Clusterize(), GetCluster(), EventProxy::GetData(), mCluster, Cluster::mClusterSize, mData, mExclude, Data::mNeighbours, Cluster::mParent, and Data::mProtoCluster.

2.4.3.3 GetCluster()

```
Cluster* DataProxy::GetCluster ( ) [inline]
```

Get a pointer to this data-proxy's ultimate parent cluster (or null if unclustered.

Returns

A pointer to this data-proxy's ultimate parent cluster

Definition at line 51 of file DataProxy.hpp.

References Cluster::GetParent(), and mCluster.

Referenced by Clusterize().

2.4.3.4 operator=() [1/2]

Deleted assignment operator.

Returns

Reference to this, for chaining calls

Parameters

aOther Anonymous argument

2.4.3.5 operator=() [2/2]

Default move-assignment constructor.

Returns

Reference to this, for chaining calls

Parameters

aOther Anonymous argument	aOther
---------------------------	--------

The documentation for this class was generated from the following files:

- include/BayesianClustering/DataProxy.hpp
- src/BayesianClustering/DataProxy.cpp

2.5 Event Class Reference

A class which holds the raw event data and global parameters.

```
#include <Event.hpp>
```

Public Member Functions

• Event ()

Default Constructor.

• Event (const Event &aOther)=delete

Deleted copy constructor.

Event & operator= (const Event &aOther)=delete

Deleted assignment operator.

• Event (Event &&aOther)=default

Default move constructor.

• Event & operator= (Event &&aOther)=default

Default move-assignment constructor.

• void Preprocess ()

All the necessary pre-processing to get the event ready for an RT-scan.

- void ScanRT (const std::function < void(const EventProxy &, const double &, const double &) > &aCallback)
 Run the scan.
- void Clusterize (const double &R, const double &T, const std::function < void(const EventProxy &) > &a ←
 Callback)

Run clusterization for a specific choice of R and T.

void LoadCSV (const std::string &aFilename)

Load an event from given file.

• void WriteCSV (const std::string &aFilename)

Save an event to a file.

Public Attributes

std::vector < Data > mData

The collection of raw data points.

2.5 Event Class Reference 39

2.5.1 Detailed Description

A class which holds the raw event data and global parameters.

Definition at line 16 of file Event.hpp.

2.5.2 Constructor & Destructor Documentation

2.5.2.1 Event() [1/2]

Deleted copy constructor.

Parameters

aOther	Anonymous argument
--------	--------------------

2.5.2.2 Event() [2/2]

Default move constructor.

Parameters

```
aOther | Anonymous argument
```

2.5.3 Member Function Documentation

2.5.3.1 Clusterize()

Run clusterization for a specific choice of R and T.

Parameters

R	The R parameter for clusterization
T	The T parameter for clusterization
aCallback	A callback for the clusterization results

Definition at line 49 of file Event.cpp.

References EventProxy::Clusterize(), and Preprocess().

2.5.3.2 LoadCSV()

Load an event from given file.

Parameters

aFilename	The name of the file to load

Definition at line 103 of file Event.cpp.

References mData.

Referenced by Event().

2.5.3.3 operator=() [1/2]

Deleted assignment operator.

Returns

Reference to this, for chaining calls

Parameters

aOther Anonymous argument	t
---------------------------	---

2.5 Event Class Reference 41

2.5.3.4 operator=() [2/2]

Default move-assignment constructor.

Returns

Reference to this, for chaining calls

Parameters

aOther Anonymous argument

2.5.3.5 ScanRT()

```
void Event::ScanRT (  {\it const std::function} < {\it void(const EventProxy \&, const double \&, const double \&)} > \& \\ {\it aCallback} \ )
```

Run the scan.

Parameters

aCallback	A callback for each RT-scan result

Definition at line 33 of file Event.cpp.

References mData, and Preprocess().

2.5.3.6 WriteCSV()

Save an event to a file.

Parameters

aFilename	The name of the file to which to save

Definition at line 141 of file Event.cpp.

 $References\ Configuration :: to Physical Units (),\ and\ Configuration :: to Physical Units (),\ and\ Configuration :: to Physical Units ().$

The documentation for this class was generated from the following files:


- · include/BayesianClustering/Event.hpp
- src/BayesianClustering/Event.cpp

2.6 EventProxy Class Reference

A lightweight wrapper for the event to store clusters for a given scan.

#include <EventProxy.hpp>

Collaboration diagram for EventProxy:



Public Member Functions

EventProxy (Event &aEvent)

Default constructor.

EventProxy (const EventProxy &aOther)=delete

Deleted copy constructor.

• EventProxy & operator= (const EventProxy &aOther)=delete

Deleted assignment operator.

EventProxy (EventProxy &&aOther)=default

Default move constructor.

EventProxy & operator= (EventProxy &&aOther)=default

Default move-assignment constructor.

• void CheckClusterization (const double &R, const double &T)

Run validation tests on the clusters.

 void ScanRT (const std::function < void(const EventProxy &, const double &, const double &) > &aCallback, const uint8_t &aParallelization=1, const uint8_t &aOffset=0)

Run an RT-scan.

void Clusterize (const double &R, const double &T, const std::function< void(const EventProxy &) > &a←
 Callback)

Run clusterization for a specific choice of R and T.

void UpdateLogScore ()

Update log-probability after a scan.

DataProxy & GetData (const std::size_t &aIndex)

Get the proxy for the Nth neighbour of this data-point.

Public Attributes

std::vector < DataProxy > mData

The collection of lightweight data-point wrappers used by this event wrapper.

• std::vector< Cluster > mClusters

The collection of clusters found by this scan.

• std::size_t mClusteredCount

The number of clustered data-points.

std::size_t mBackgroundCount

The number of background data-points.

• std::size_t mClusterCount

The number of non-Null clusters.

double mLogP

The log-probability density associated with the last scan.

Private Attributes

· const Event & mEvent

2.6.1 Detailed Description

A lightweight wrapper for the event to store clusters for a given scan.

Definition at line 15 of file EventProxy.hpp.

2.6.2 Constructor & Destructor Documentation

2.6.2.1 EventProxy() [1/3]

Default constructor.

Parameters

aEvent An event for which this is a lightweight proxy

Definition at line 14 of file EventProxy.cpp.

References mClusters, Event::mData, and mData.

2.6.2.2 EventProxy() [2/3]

Deleted copy constructor.

Parameters

```
aOther Anonymous argument
```

2.6.2.3 EventProxy() [3/3]

Default move constructor.

Parameters

```
aOther Anonymous argument
```

2.6.3 Member Function Documentation

2.6.3.1 CheckClusterization()

```
void EventProxy::CheckClusterization ( const double & R, const double & T)
```

Run validation tests on the clusters.

Parameters

R	The R of the last run scan
Т	The T of the last run scan

Definition at line 22 of file EventProxy.cpp.

 $References\ GetData(),\ mBackgroundCount,\ mClusterCount,\ mClusters,\ and\ mData.$

2.6.3.2 Clusterize()

Run clusterization for a specific choice of R and T.

Parameters

R	The R parameter for clusterization
T	The T parameter for clusterization
aCallback	A callback for the clusterization results

Definition at line 123 of file EventProxy.cpp.

References mClusters, Event::mData, mData, and UpdateLogScore().

Referenced by Event::Clusterize().

2.6.3.3 GetData()

Get the proxy for the Nth neighbour of this data-point.

Returns

A reference to the neighbour data-proxy

Parameters

alndex	The index of the neighbour we are looking for

Definition at line 59 of file EventProxy.hpp.

References mData.

Referenced by CheckClusterization(), and DataProxy::Clusterize().

2.6.3.4 operator=() [1/2]

Deleted assignment operator.

Returns

Reference to this, for chaining calls

Parameters

aOther Anonymous argu	ment
-----------------------	------

2.6.3.5 operator=() [2/2]

Default move-assignment constructor.

Returns

Reference to this, for chaining calls

Parameters

aOther	Anonymous argument
--------	--------------------

2.6.3.6 ScanRT()

Run an RT-scan.

Parameters

aCallback	A callback for each RT-scan result
aParallelization	The stride with which we will iterate across RT parameters
aOffset	The starting point for the strides as we iterate across RT parameters

Definition at line 94 of file EventProxy.cpp.

References Configuration::dT(), Configuration::Instance, Configuration::maxScanT(), Configuration::Rbins(), and Configuration::Tbins().

The documentation for this class was generated from the following files:

- · include/BayesianClustering/EventProxy.hpp
- src/BayesianClustering/EventProxy.cpp

2.7 Cluster::Parameter Struct Reference

A struct representing the cluster parameters.

```
#include <Cluster.hpp>
```

Public Member Functions

• Parameter ()

Default constructor.

Parameter & operator+= (const Parameter &aOther)

Add another set of parameters to this set.

• double log_score () const

Convert the parameters to a log-probability.

Public Attributes

PRECISION A

Parameter A defined in the math.

PRECISION Bx

Parameter Bx defined in the math.

· PRECISION By

Parameter By defined in the math.

• PRECISION C

Parameter C defined in the math.

PRECISION logF

Parameter logF defined in the math.

2.7.1 Detailed Description

A struct representing the cluster parameters.

Definition at line 19 of file Cluster.hpp.

2.7.2 Member Function Documentation

2.7.2.1 log_score()

```
double Cluster::Parameter::log_score ( ) const
```

Convert the parameters to a log-probability.

Returns

the log-probability of this set of cluster parameters

Definition at line 35 of file Cluster.cpp.

2.7.2.2 operator+=()

Add another set of parameters to this set.

Parameters

aOther	Another set of parameters to add to this set
--------	--

Returns

Reference to this, for chaining calls

Definition at line 16 of file Cluster.cpp.

References A, Bx, By, C, and logF.

The documentation for this struct was generated from the following files:

- · include/BayesianClustering/Cluster.hpp
- src/BayesianClustering/Cluster.cpp

2.8 ProgressBar Struct Reference

A utility progress-bar.

```
#include <ProgressBar.hpp>
```

Public Member Functions

ProgressBar (const std::string &aLabel, const uint32_t &aMax)

Constructor.

virtual ∼ProgressBar ()

Destructor.

void operator++ ()

Postfix increment.

void operator++ (int aDummy)

Prefix increment.

Public Attributes

· float mBlockSize

The size of each increment.

float mNextThreshold

The next threshold at which we will write a block to stdout.

std::size_t mCount

The number of times we have incremented.

• std::chrono::high_resolution_clock::time_point mStart

A timer for end-of-task stats.

2.8.1 Detailed Description

A utility progress-bar.

Definition at line 6 of file ProgressBar.hpp.

2.8.2 Constructor & Destructor Documentation

2.8.2.1 ProgressBar()

Constructor.

Parameters

aLabel	A description of the task being timed
aMax	The number of calls equalling 100%

Definition at line 7 of file ProgressBar.cpp.

2.8.3 Member Function Documentation

2.8.3.1 operator++()

Prefix increment.

Parameters

aDummy	Anonymous argument
--------	--------------------

Definition at line 27 of file ProgressBar.cpp.

References operator++().

The documentation for this struct was generated from the following files:

- include/Utilities/ProgressBar.hpp
- src/Utilities/ProgressBar.cpp

2.9 ProgressBar2 Struct Reference

A utility code timer.

```
#include <ProgressBar.hpp>
```

Public Member Functions

• ProgressBar2 (const std::string &aLabel, const uint32_t &aMax)

Constructor.

virtual ∼ProgressBar2 ()

Destructor.

void operator++ ()

Postfix increment.

void operator++ (int aDummy)

Prefix increment.

Public Attributes

• std::chrono::high_resolution_clock::time_point mStart A timer for end-of-task stats.

2.9.1 Detailed Description

A utility code timer.

Definition at line 34 of file ProgressBar.hpp.

2.9.2 Constructor & Destructor Documentation

2.9.2.1 ProgressBar2()

Constructor.

Parameters

	aLabel	A description of the task being timed
aMax The number of calls equalling 100°		The number of calls equalling 100%

Definition at line 32 of file ProgressBar.cpp.

2.9.3 Member Function Documentation

2.9.3.1 operator++()

Prefix increment.

Parameters

aDummy	Anonymous argument

Definition at line 44 of file ProgressBar.cpp.

References operator++().

The documentation for this struct was generated from the following files:

- include/Utilities/ProgressBar.hpp
- src/Utilities/ProgressBar.cpp

Index

alpha	SetRBins, 20
Configuration, 9	SetSigmaParameters, 2
	SetTBins, 21
CheckClusterization	SetValidate, 22
EventProxy, 44	SetZoom, 22
Cluster, 3	sigmabins, 22
Cluster, 4	sigmabins2, 23
GetParent, 4	sigmacount, 24
operator+=, 5	sigmaspacing, 24
Cluster::Parameter, 47	Tbins, 24
log_score, 47	toAlgorithmUnits, 24
operator+=, 48	toAlgorithmX, 25
Clusterize	toAlgorithmY, 25
DataProxy, 36	toPhysicalUnits, 26
Event, 39	toPhysicalX, 26
EventProxy, 44	toPhysicalY, 27
ClusterR	validate, 27
Configuration, 10	,
ClusterT	Data, 28
Configuration, 10	Data, 29, 30
Configuration, 5	dPhi, 30
alpha, 9	dR, 31
ClusterR, 10	dR2, 31
ClusterT, 10	operator<, 31
dR, 10	operator=, 32
dT, 11	Preprocess, 33
FromCommandline, 11	DataProxy, 33
inputFile, 12	Clusterize, 36
log_probability_sigma, 12	DataProxy, 35
logAlpha, 13	GetCluster, 37
logGammaAlpha, 13	operator=, 37
logPb, 13	dPhi
logPbDagger, 14	Data, 30
max2R, 14	dR
max2R2, 14	Configuration, 10
maxR, 15	Data, 31
maxR2, 15	dR2
maxScanR, 15	Data, 31
maxScanT, 16	dT
minScanR, 16	
minScanT, 16	Configuration, 11
outputFile, 17	Event, 38
probability_sigma, 17	Clusterize, 39
	,
Rbins, 18	Event, 39 LoadCSV, 40
scale2, 18	ŕ
SetCentre 10	operator=, 40
SetCentre, 19	ScanRT, 41
SetInputFile, 19	WriteCSV, 41
SetOutputFile, 19	EventProxy, 42
SetPb. 20	CheckClusterization, 44

54 INDEX

Clusterize, 44 EventProxy, 43, 44 GetData, 45 operator=, 45, 46 ScanRT, 46	Data, 32 DataProxy, 37 Event, 40 EventProxy, 45, 46 outputFile
FromCommandline Configuration, 11	Configuration, 17 Preprocess
GetCluster DataProxy, 37 GetData EventProxy, 45 GetParent Cluster, 4 inputFile	Data, 33 probability_sigma Configuration, 17 ProgressBar, 48 operator++, 50 ProgressBar, 49 ProgressBar2, 50 operator++, 51
Configuration, 12	ProgressBar2, 51
LoadCSV Event, 40 log_probability_sigma	Rbins Configuration, 18
Configuration, 12 log_score Cluster::Parameter, 47	scale2 Configuration, 18 ScanRT
logAlpha Configuration, 13 logGammaAlpha	Event, 41 EventProxy, 46 SetAlpha
Configuration, 13 logPb	Configuration, 18 SetCentre Configuration, 19
Configuration, 13 logPbDagger Configuration, 14	SetInputFile Configuration, 19 SetOutputFile
max2R Configuration, 14 max2R2	Configuration, 19 SetPb Configuration, 20
Configuration, 14 maxR	SetRBins Configuration, 20
Configuration, 15 maxR2 Configuration, 15	SetSigmaParameters Configuration, 21 SetTBins
maxScanR Configuration, 15 maxScanT	Configuration, 21 SetValidate Configuration, 22
Configuration, 16 minScanR Configuration, 16	SetZoom Configuration, 22 sigmabins
minScanT Configuration, 16	Configuration, 22 sigmabins2
operator< Data, 31	Configuration, 23 sigmacount Configuration, 24
operator++ ProgressBar, 50 ProgressBar2, 51	sigmaspacing Configuration, 24
operator+= Cluster, 5	Tbins Configuration, 24
Cluster::Parameter, 48 operator=	toAlgorithmUnits Configuration, 24

INDEX 55

toAlgorithmX
Configuration, 25
toAlgorithmY
Configuration, 25
toPhysicalUnits
Configuration, 26
toPhysicalX
Configuration, 26
toPhysicalY
Configuration, 27
validate
Configuration, 27
WriteCSV
Event, 41